

DM6430 Driver for Windows 98/NT4/2000/XP

User's Manual

version 4.0



SWM-640010003
Rev. B



RTD Embedded Technologies, INC.

103 Innovation Blvd.
State College, PA 16803-0906

Phone: +1-814-234-8087

FAX: +1-814-234-5218

E-mail

sales@rtd.com

techsupport@rtd.com

web site

<http://www.rtd.com>

Revision History

08/06/2003	revision A issued Documented for ISO9000
09/12/2003	revision B issued Version 4.0 released Company name changed Windows 2000/XP support added Windows 95 support removed interface of the following functions changed: <ul style="list-style-type: none">- OpenBoard6430- SetPacerClock6430- SetBurstClock6430- SetUserClock6430

DM6430 Driver for Windows 98/NT4/2000/XP

Published by:

RTD Embedded Technologies, Inc.

103 Innovation Blvd.

State College, PA 16803-0906

Copyright 2003 RTD Embedded Technologies, Inc.

All rights reserved

Printed in U.S.A.

The RTD Logo is a registered trademark of RTD Embedded Technologies. cpuModule and utilityModule are trademarks of RTD Embedded Technologies. PS/2, PC/XT, PC/AT and IBM are trademarks of International Business Machines Inc. MS-DOS, Windows, Windows 95, Windows 98, Windows NT, Windows 2000 and Windows XP are trademarks of Microsoft Corp. PC/104 is a registered trademark of PC/104 Consortium. All other trademarks appearing in this document are the property of their respective owners.

Table of Contents

TABLE OF CONTENTS	4
INTRODUCTION	5
INSTALLATION	6
INSTALLATION OF THE DRIVER AND EXAMPLE PROGRAMS	6
THE DM6430 BOARD DRIVER.....	7
THE DRIVER CONFIGURATION.....	7
INSTALLING A SECOND BOARD IN THE SYSTEM	8
WORKING WITH OTHER BOARDS USING THE WINRT DRIVER	8
USING WINDOWS REGISTRY KEYS	9
THE DRIVER API FUNCTIONS	11
USING THE DRIVER WITHOUT THE WINDOWS-GUI	12
DM6430 FEATURES.....	13
MEASUREMENT SCENARIOS	13
CHANNEL-GAIN CIRCUITRY	13
INTERRUPTS	16
DIRECT MEMORY ACCESS (DMA)	18
DRIVER API FUNCTION GROUPS	19
DRIVER INITIALIZATION FUNCTIONS	19
GENERAL BOARD CONTROL FUNCTIONS	19
FIFO MANIPULATION	19
DMA FUNCTIONS.....	19
A/D CONVERTER.....	19
D/A CONVERTER.....	20
PACER CLOCK HANDLING	20
BURST CLOCK HANDLING	20
ABOUT COUNTER FUNCTIONS	20
SAMPLE COUNTER FUNCTIONS.....	20
DIGITAL I/O FUNCTIONS	20
INTERRUPT HANDLING	20
AUTOINCREMENT DATA HANDLING.....	21
USER TIMER-COUNTER FUNCTIONS	21
CHANNEL-GAIN TABLE/LATCH MANIPULATION	21
EXTERNAL TRIGGER CONFIGURATION FUNCTIONS	21
ERROR HANDLING FUNCTIONS.....	21
ALPHABETICAL DRIVER API FUNCTIONS REFERENCE	22
EXAMPLE PROGRAMS REFERENCE	56
WIN32 CONSOLE APPLICATIONS	56
WIN32 WINDOWS APPLICATIONS	57
LIMITED WARRANTY	58

Introduction

The DM6430 data acquisition board Windows 98/NT4.0/2000/XP driver was designed for programmers who write Windows-based application programs for the RTD's DM6430 board.

The driver provides an Application Programming Interface with a lot of function calls to perform all the data acquisition tasks of the board users.

The board driver is based on the BlueWater System's WinRT device driver kit.

There are example programs to demonstrate the various board features and the usage of the driver API. The example programs are written in Microsoft Visual C++ ver. 6.0.

Installation

Installation of the Driver and Example Programs

Before installing the driver and example program files, you need to install the DM6430 board in your PC. Please follow the instructions of the manufacturer, how to install the board in a computer.

To install the drivers for the DM6430 under Windows 98/2000/XP you need the installation diskette 0. The readme.txt file on this diskette describes the necessary installation steps.

For Windows NT4.0 the installation diskette 0 is not needed.

On the installation diskette 1 you can find the **Setup.exe** program, which installs on your PC the DM6430 board driver and example programs. The setup program automatically detects your operating system and installs the appropriate files on your PC.

After starting the setup, please follow the instructions on the screen to install the programs. You can select the directory where to install the files.

The setup also adds to the 'Start menu' under the 'Programs' folder of your Windows system the 'RTD Embedded Technologies' folder. It contains shortcuts to the example programs, the driver configuration utility and the readme.txt file.

The example programs will be installed in the target directory under the 'Examples' folder. This folder contains the example program sources for the DM6430 board, and the project files for Microsoft Visual C++ users to rebuild the programs. The example programs are compiled with the Microsoft Visual C++ ver. 6.0. In case of different version of Visual C is installed on your PC, please rebuild the executable files.

Uninstallation: you can uninstall the DM6430 driver and example programs under the 'Control panel' with the 'Add/Remove Programs' tool.

The DM6430 board driver

The RTD's DM6430 board driver handles the hardware through the BlueWater's WinRT driver. The WinRT driver provides the low-level access to the board, and the RTD's Drvr6430.dll provides the device API for the programmers, and communicates with the hardware through the WinRT driver.

The RTD board drivers has multi-board feature. It means that it is possible to use more than one board in the system.

The base address of the DM6430 board can be set by DIP-switch. If you are using multiple boards in your system, you need assign a different base address to each board. The IRQ and DMA channels are set programmatically. When you install a WinRT driver for the board, you must select the IRQ and DMA channel, and during the operating of the board must be used this IRQ and DMA channels.

Each board requires a unique WinRT device to handle the hardware. Also the second DMA channel of the DM6430 board requires a unique device. The maximum number of devices is 32.

The DM6430 board has a dual-DMA feature (working with two DMA channels parallel). This operating mode requires a different driver device for the second DMA channel. So every DM6430 board uses two WinRT devices one after the other, and they are using successive driver ID's.

During the installation the Setup.exe program set the default driver values:

Board 1 : 0x300 base address, DMA channel 5, DMA buffer size 0x4000 and IRQ 11
Board 1 2'nd DMA channel: DMA channel 6, DMA buffer size 0x4000.

If these settings are not proper to your PC configuration, you can modify the settings with the **Drvr_cfg.exe** program in Windows NT4.0.

In case of Windows 98/2000/XP the operating system uses a WDM driver and it can be configured in the Control Panel/System/[Hardware]/Device Manager.

The Driver Configuration

As in the previous chapter mentioned, after installing the driver the default settings are used.

If these settings are not proper to your PC configuration, or there are other RTD boards used, you can modify the settings.

Under Windows NT driver can be configured with the **Drvr_cfg.exe** program. This program is installed on your PC during the setup process and it can be started from the Start menu.

Program options:

- Device number: The number of device, which handles the board. Each board has a unique device number between 0 and 9.
- I/O port base address: The I/O base address of the board.
- IRQ number: The IRQ number using of the board.
- DMA channel: The DMA channel using of the board.
- DMA buffer size: The DMA buffer size. It should not be more than 64k.
- Dual DMA channel: If this check-box is set, it means that this is a driver for the second DMA channel of the same board.

- Register: Press this button to store the settings in the Windows registry.
- Refresh: Press this button to get the information from the registry about the selected device number.

Under Windows 98/2000/XP same changes can be made using Control Panel/System/[Hardware]/Device Manager/WinRT Devices.

Do not forget, that all boards are required different driver devices, and in your C++ program must be used the DEVICE_NO according to the driver device number.

Installing a second board in the system

It is possible to use more than one board in the system using the RTD's data acquisition board drivers. Please follow the next steps to install a multi-board – system:

- Install the first board with all software and make sure that everything is working well.
- Place the second board in an empty slot in the PC, and switch on the computer.
Windows NT4.0: After the system startup start the installation program and answer 'YES' to the next board installation question. Restarting the system with the two-board example program is possible to test the working of both boards. Please note that during the second board installation the driver and example program files will be refreshed thus you need to save the important changes before starting the install.
Windows 98/2000/XP: You need only the installation diskette 0 to install the next boards. Follow the steps described in the readme.txt file on diskette 0.

Working with Other Boards Using the WinRT Driver

As you may have in your computer other RTD boards, which uses the WinRT driver, or a board from other manufacturer with WinRT, our installation program automatically detects the WinRT settings from the system registry file, and installs the appropriate (next) WinRT device. You can see an informational dialog box about this issue during the setup.

As an application written for the DM6430 board should know which WinRT device is assigned to the board, the installation program generates the file wrtdev.txt in the 'Examples' directory containing the actual device number. The example programs are reading this file at the startup to identify this number.

If the other board in your system, which uses the WinRT driver does not handle the situation when there is other WinRT-based application, install this board firstly, and then install the DM6430 which handles correctly this state.

Using Windows registry keys

The RTD board drivers are using the next registry keys:

Windows NT 4.0:

```
HKEY_LOCAL_MACHINE
|
|-- System
|   |
|   |-- CurrentControlSet
|       |
|       |-- Services
|           |
|           |-- WinRT
|               |
|               |-- WinRTdev0    (one per device)
|                   |
|                   |-- Parameters
|                       |
|                       |-- Section0
|
|               |-- WinRTdev1
|                   |
|                   |-- Parameters
|                       |
|                       |-- Section0
|
```

Windows 98 Enum key path:

```
HKEY_LOCAL_MACHINE
|
|-- Enum
```

Windows 98 Class key path:

```
HKEY_LOCAL_MACHINE
|
|-- System
|   |
|   |-- CurrentControlSet
|       |
|       |-- Services
|           |
|           |-- Class
|               |
|               |-- WinRTDevices
```

Windows 2000/XP device class information:

```
HKEY_LOCAL_MACHINE
|
|-- System
|   |
|   |-- CurrentControlSet
|       |
|       |-- Control
|           |
|           |-- Class
|               |
|               |-- {D695ED6A-630D-4D83-D8B-F1F0AC107AD0}
|               |
|               |-- 0001
```

The Driver Api Functions

The resources on the DM6430 board can be accessed from Windows through the driver API (Application Programming Interface) functions. The executable code of these functions is located in the Drvr6430.dll file. To write applications using the API functions you must include the Reg6430.H header file, and link the program with the Drvr6430.lib import library file. In the example programs you can find different examples how to use the driver.

Using the Driver without the Windows-GUI

This driver is based on the Win32 system, and can run only under Windows. However, the user, who is not familiar with the Windows Graphical User Interface, can use the driver API functions in Win32 console applications, which has an MS-DOS like text-mode interface.

In console applications is not necessary to use the Windows graphical environment, but all the driver's API functions are accessible.

The Microsoft Visual C++ compiler supports writing console applications.

DM6430 Features

Measurement Scenarios

Through selecting different options for A/D Conversion Trigger (SetConversionSelect6430), Burst Clock Start Trigger (SetBurstTrigger6430), and creating different Channel-Gain Tables, you have innumerable sampling scenarios. The following bullets try to enumerate only the most frequently used measurement setups.

❑ **Single Conversion**

In this mode, a single channel is sampled whenever StartConversion6430 is called. The Channel Gain Latch (see SetChannelGain6430) specifies the channel to sample. This is the easiest scenario of all. It can be used in a variety of applications, such as sample every time a key is pressed on the keyboard, sample with each iteration of a loop, or watch the system clock and sample every five seconds.

❑ **Multiple Conversions**

In this mode, conversions are continuously performed at the rate of the Pacer Clock, or other selected A/D Conversion Signal rate. The pacer clock can be internal or external. The maximum rate supported by the board is 100KHz. If you use the internal pacer clock, you must program it to run at the desired rate (SetPacerClock6430).

This mode is ideal for filling arrays, acquiring data for a specified period, and taking a specified number of samples.

❑ **Random Channel Scan**

In this mode, the Channel-Gain Table is incrementally scanned through, with each selected A/D Conversion Signal pulse starting a conversion at the channel and gain specified in the current table entry. Before starting a conversion sequence Channel Gain Table, you need to load the table with the desired data. Then make sure that the Channel-Gain Table is enabled by the function EnableTables6430. This enables the A/D and Digital portion of the Channel Gain Table as well. Each rising edge of selected A/D Conversion Signal starts a conversion using the current Channel Gain data and then increments to the next position in the table. When the last entry is reached, the next pulse starts the table over again.

❑ **Programmable Burst**

In this mode, a single trigger initiates a scan of the entire Channel-Gain Table. Before starting a burst of the Channel-Gain Table, you need to load the table with the desired data. Then enable the Channel-Gain Table by EnableTable6430.

Burst is used when you want one sample from a specified number of channels for each trigger. The burst trigger starts the Burst Clock and the Burst Clock initiates each conversion. At high speeds, the burst mode emulates simultaneous sampling of multiple input channels. For time critical simultaneous sampling applications, a simultaneous sample-and-hold board can be used (SS8 eight-channel boards are available from Real Time Devices).

❑ **Programmable Multi-Scan**

This mode - when the A/D Conversion Start Signal is the Burst Clock - lets you scan the Channel Gain Table after a Burst Clock Start Signal. When the Channel Gain Table is empty, the Burst Clock is stopped, and will wait for a new Start Signal.

Channel-Gain Circuitry

Channel-Gain Tables are traditionally for implementing random channel scan analog input on boards where a single A/D converter is multiplexed for 8, 16 or more analog input channels.

The Channel-Gain Circuitry embeds a 1024x24 bit on-board memory (Channel Scan Memory), called *Channel-Gain Table* (CGT) for historical reasons. Every 24-bit row (entry) in a CGT is an instruction executed by the Channel-Gain circuitry. Execution happens at a programmable rate. Channel-Gain Latch (CGL), provided for easy, single channel analog input, can be perceived as a special, single row CGT for the following description. Unless explicitly indicated, explanation holds for the CGL, as well.

The table below pictures the format of a CGT entry:

DO	Skip	Pause	Se/Diff	Gain	Channel
8 bits	1 bit	1 bit	1 bit	3 bits	4 bits

Channel Analog Input Channel

Specifies the Analog Input channel to sample. Depending on your configuration you may have 8 differential channels (AIN1...AIN8), or 16 Single-Ended channels (AIN1...AIN16)

Gain Analog Input Gain

This field specifies the gain to apply to the input. Available choices are 1x, 2x, 4x, 8x.

Se/Diff Analog Input Type

Pause Pause Bit

If this bit is enabled by the SetADPauseEnable6430 function, execution of the Channel-Gain Table stops *after* executing this entry. Execution is resumed with the next CGT entry when the programmed Pacer Clock start trigger occurs.

EXAMPLE: Pause Bit can be used when you have two sequence of entries, each to be executed on a different event (trigger). Suppose that CGT is driven by the Pacer Clock, and the Pacer Clock is started on the External Trigger. The External Trigger comes from a device, whose pulses indicate two different events. Odd pulses indicate an event, on which you want to react by sampling AIN1 and AIN2, on even pulses you want to sample AIN3, AIN4 and AIN5. In this case, you would create a 5 entry CGT:

Entry #1: AIN1, Pause Bit = 0
Entry #2: AIN2, Pause Bit = 1
Entry #3: AIN3, Pause Bit = 0
Entry #4: AIN4, Pause Bit = 0
Entry #5: AIN5, Pause Bit = 1

In this case, the first pulse on the External Trigger line starts executing the CGT at the rate of the Pacer Clock. After executing the first two entries, execution stops and is waiting for the next External Trigger pulse. The second pulse resumes execution, and entries #3, #4 and #5 are executed at the rate of the Pacer Clock. Execution pauses again, after executing entry #5. A third External trigger pulse continues execution with entry #1, and so on.

NOTE: When the Channel-Gain Latch is used, or in burst mode, Pause Bit is ignored.

Skip

Skip Bit

When the Skip Bit is set, the entry is skipped, which means that the A/D conversion is performed but the resulting sample is not written into the A/D FIFO. This feature provides a way to sample multiple channels at different rates without saving unwanted data.

EXAMPLE: In this example, we want to sample AIN1 in every second and AIN4 in every three seconds. For this end, we must create CGT with six entries:

Entry #1: AIN1, Skip Bit = 0
Entry #2: AIN4, Skip Bit = 1
Entry #3: AIN1, Skip Bit = 0
Entry #4: AIN4, Skip Bit = 1
Entry #5: AIN1, Skip Bit = 0
Entry #6: AIN4, Skip Bit = 0

Next, we set the Pacer Clock to run at 2 Hz (0.5 seconds). This allows us to sample each channel once per second, the maximum sampling rate required by one of the channels (pacer clock rate = number of different channels sampled x fastest sample rate).

The first Pacer Clock pulse starts an A/D conversion according to the parameters set in the first entry of the Channel-Gain Table, and each successive clock pulse incrementally steps through the table entries. The first clock pulse takes a sample on AIN1. The second pulse looks at the second entry in the table and sees that the Skip Bit is set. Sample is taken, but is not stored in the FIFO. The third pulse takes a sample on AIN1 again, the fourth pulse skips the next entry, and the fifth pulse takes our third reading on AIN1. On the sixth pulse, the Skip Bit is disabled, AIN4 is sampled and sample is stored to the FIFO. Then the sequence starts over again with entry #1. Samples are not stored when they are not wanted, saving memory and eliminating the need to throw away unwanted data.

NOTE: When the Channel-Gain Latch is used, Skip Bit is ignored.

DO

8-Bit Digital Table

The digital portion of the Channel-Gain Table, also referred to as Digital Table, can be used to control input expansion boards such as the TMX32 Analog Input Expansion board. The expansion board is driven at the same speed as the A/D conversions are performed, with no software overhead.

EXAMPLE: Let us consider the following simple example on driving an analog input expansion board.

In this example, we have a TMX32 expansion board connected to AIN1 on the DM6430. We have three signals to sample, one is connected to the first channel of the expansion board (EAIN1), the second is connected to the fourth channel of the expansion board (EAIN4) and the third is connected directly to AIN2 of the DM6430.

We need to create the following Channel-Gain Table:

Entry #1: AIN1, gain=1, DO=0
Entry #2: AIN1, gain=4, DO=3
Entry #3: AIN2, gain=1, DO=3

Execution, starting with entry #1, samples AIN1 and simultaneously outputs 0 on Digital Port 1. This will cause the expansion board to switch to EAIN1.

Entry #2 will sample AIN1, which is now connected to EAIN1, and simultaneously outputs 3 on Digital Port 1. As a result, the expansion board switches to EAIN4.

Next, entry #3 samples AIN2 and outputs 3 on Digital Port 1, which makes the expansion board to switch (again) to EAIN4.

When executing entry #1 again, AIN1 is sampled which is now connected to EAIN4, and so on.

NOTE: If you only need to use the A/D part of the table, you do not have to program the Digital Table. However, if you only want to use the Digital part of the table, you must program the A/D part of the table.

NOTE: When the Channel-Gain Latch is used, Digital Table is ignored.

When using the Channel Gain Table, you should group your entries to maximize the throughput of your module. Low-level input signals and varying gains are likely to drop the throughput rate because low level inputs must drive out high level input residual signals. To maximize throughput:

- ☐ Keep channels configured for a certain range grouped together, even if they are out of sequence.
- ☐ Use external signal conditioning if you are performing high speed scanning of low level signals. This increases throughput and reduces noise.
- ☐ If you have room in the channel-gain table, you can make an entry twice to make sure that sufficient settling time has been allowed and an accurate reading has been taken. Set the skip bit for the first entry so that it is ignored.
- ☐ For best results, do not use the channel-gain table when measuring steady-state signals. Use the single convert mode to step through the channels.

Interrupts

Controller can receive interrupt request from up to 15 sources. These 15 sources cover the most important internal signals of the board plus 2 external signals:

- ☐ A/D Sample Counter Countdown

Interrupt is generated when the A/D Sample Counter counts down to zero.

This interrupt can be used to count more than 65535 samples by counting the turnovers of the Sample Counter.

- ❑ A/D Start Convert
Interrupt is generated when a conversion is started.
- ❑ A/D End Of Convert
Interrupt is generated when an end of convert is issued by the A/D converter.
- ❑ A/D FIFO Write
Interrupt is generated when sample enters the A/D FIFO.
This interrupt can be used for reading and processing samples real-time.
- ❑ A/D FIFO Half Full
Interrupt is generated when the A/D FIFO is half full.
- ❑ A/D DMA Done
Interrupt is generated when the A/D DMA done flag goes high.
- ❑ CGT Reset
Interrupt is generated when the Channel-Gain Table recycles execution to the first table entry.
This interrupt can be used for reading and processing a burst of samples from different channels real-time.
- ❑ CGT Pause
Interrupt is generated when Channel-Gain Table execution is paused waiting for a new trigger.
- ❑ External Pacer Clock
Interrupt is generated when the external pacer clock line is pulsed.
- ❑ External Trigger
Interrupt is generated when the external trigger line is pulsed.
- ❑ Digital Interrupt
Interrupt is generated when the Advanced Digital Trigger signals a Digital Interrupt.
This interrupt can be used to detect (and react on) certain patterns on Digital Input Port 0.
- ❑ User Timer/Counter 0 Out
- ❑ User Timer/Counter 0 Out, inverted
- ❑ User Timer/Counter 1 Out
Interrupt is generated on the ticks of User T/C0 (i.e., when the counter counts down to zero).
This interrupt gives you a general-purpose means of measuring real time, frequency, or counting events. It is also intended to use for Pulse output generation.
- ❑ Digital Input FIFO Half Full
Interrupt is generated when the Digital Input FIFO is half full.
- ❑ Digital Input FIFO Write
Interrupt is generated when sample enters the Digital Input FIFO.

To service interrupts with the DM6430 Driver is very simple.

Actually, when you install your interrupt handler, it is not a real Interrupt Service Routine, since you can not do that under Windows. Your handler is an ordinary routine, which is called by the real Interrupt Service Routine implemented by the DM6430 driver. The driver's Interrupt Service Routine schedules your interrupt handler for execution as a separate thread, acknowledges the interrupt to the board's interrupt controller and returns. After returning, the scheduled thread starts executing your interrupt handler.

Direct Memory Access (DMA)

DMA transfers data between peripheral device and PC memory without using the processor as an intermediate. This method allows very fast data transfer rates.

The DM6430 driver provides an interface for the user to handle the DMA channels of the board. The driver handles the dual-DMA mode of the DM6430, too.

The following program steps are necessary to use the DMA:

- ❑ Initialize the board, setup triggering modes.
- ❑ Install the DMA handler.
`InstallDMA6430(DEVICE_NO, &dmasetup, TRUE, 0, 0);`
- ❑ Program DMA channel.
`SetADDMA6430(DEVICE_NO, ADDMAChannel, 0);`
- ❑ Perform data collection.
- ❑ Close DMA channel.
`DeInstallDMA6430(DEVICE_NO, 0);`

To see how to use the DMA channel on the DM6430 board, see the dma and wdma example programs.

Driver API Function Groups

Driver Initialization Functions

OpenBoard
CloseBoard

General Board Control Functions

InitBoard6430
ClearBoard6430
ClearRegister6430
ReadStatus6430
LoadControlRegister6430
LoadTriggerRegister6430

FIFO Manipulation

ClearADFIFO6430
IsADFIFOEmpty6430
IsADFIFOFull6430
ClearDINFIFO6430
IsDINFIFOEmpty6430
IsDINFIFOHalf6430
IsDINFIFOFull6430
ReadDINFIFO6430

DMA Functions

InstallDMA
DeInstallDMA
StartDMA
FlushDMA
SetADDMA6430
ClearADDMADone6430
IsADDMADone6430
IsFirstADDMADone6430

A/D Converter

IsADHalted6430
IsADConverting6430
SetADSampleCounterStop6430
SetADPauseEnable6430
ReadADDData6430
StartConversion6430
SetConversionSelect6430
SetStartTrigger6430
SetStopTrigger6430
SetTriggerRepeat6430

D/A Converter

LoadDAC6430
LoadDAC26430

Pacer Clock Handling

SetPacerClock6430
IsPacerClockOn6430
SetPacerClockSource6430

Burst Clock Handling

SetBurstClock6430
IsBurstClockOn6430
SetBurstTrigger6430

About Counter Functions

IsAboutTrigger6430

Sample Counter Functions

LoadADSampleCounter6430

Digital I/O Functions

IsDigitalIRQ6430
LoadDINConfigRegister6430
ConfigDINClock6430
DINClockEnable6430
SelectRegister5812
ClearChip5812
SetPort0Direction5812
SetPort1Direction5812
LoadMask5812
LoadCompare5812
ReadDIO5812
ReadCompareRegister5812
SelectClock5812
WriteDIO5812

Interrupt Handling

InstallCallbackIRQHandler
InstallCounterIRQHandler
RemoveIRQHandler
GetIRQCounter
ClearIRQ16430
ClearIRQ26430
IsIRQ16430
IsIRQ26430

LoadIRQRegister6430
SetIRQ16430
SetIRQ26430
ClearIrq5812
EnableIrq5812
SelectIrqMode5812
IsChipIRQ5812

Autoincrement Data Handling

GetAutoincDataByte
GetAutoincDataWord

User Timer-Counter Functions

SelectTimerCounter6430
ClockMode6430
ClockDivisor6430
SetUserClock6430
ReadTimerCounter6430
DoneTimer6430

Channel-Gain Table/Latch Manipulation

ClearChannelGainTable6430
ResetChannelGainTable6430
EnableTables6430
ChannelGainDataStore6430
ReadChannelGainDataStore6430
SetChannelGain6430
LoadADTable6430
LoadDigitalTable6430

External Trigger Configuration Functions

SetTriggerPolarity6430

Error Handling Functions

GetErrorStatus6430

Alphabetical Driver API Functions Reference

C

ChannelGainDataStore6430

void ChannelGainDataStore6430(RTDHANDLE hBoard, uint16 Enable);

Description:

This routine enables the Channel Gain Data Store feature of the board.

Parameters:

hBoard:	device handle
Enable:	0 = Disable
	1 = Enable

ClearADFIFO6430

void ClearADFIFO6430(RTDHANDLE hBoard);

Description:

This routine is used to clear all the data from the A/D FIFO.

Parameters:

hBoard:	device handle
---------	---------------

ClearADDMADone6430

void ClearADDMADone6430(RTDHANDLE hBoard);

Description:

This routine is used to clear the A/D DMA done status bit.

Parameters:

hBoard:	device handle
---------	---------------

ClearBoard6430

void ClearBoard6430(RTDHANDLE hBoard);

Description:

This routine is used to clear board.

Parameters:

hBoard: device handle

ClearChannelGainTable6430

void ClearChannelGainTable6430(RTDHANDLE hBoard);

Description:

This routine is used to clear both the AD Table and the Digital Table.

Parameters:

hBoard: device handle

ClearChip5812_6430

void ClearChip5812_6430(RTDHANDLE hBoard, uchar8 SelectedChip);

Description:

This routine clears the selected DIO chip.

Parameters:

hBoard: device handle
SelectedChip: 0, 1, 2

ClearDINFIFO6430

void ClearDINFIFO6430(RTDHANDLE hBoard);

Description:

This routine is used to clear the Digital Input FIFO.

Parameters:

hBoard: device handle

ClearIRQ16430

void ClearIRQ16430(RTDHANDLE hBoard);

Description:

This routine is used to clear the IRQ 1 circuitry and status bit.

Parameters:

hBoard: device handle

ClearIRQ26430

```
void ClearIRQ26430(RTDHANDLE hBoard);
```

Description:

This routine is used to clear the IRQ 2 status bit.

Parameters:

hBoard:	device handle
---------	---------------

ClearIrq5812_6430

```
void ClearIrq5812_6430(RTDHANDLE hBoard, uchar8 SelectedChip);
```

Description:

This routine clears the selected DIO chips IRQ status bit.

Parameters:

hBoard:	device handle
SelectedChip:	0, 1, 2

ClearRegister6430

```
void ClearRegister6430(RTDHANDLE hBoard, uint16 ClearValue);
```

Description:

This routine is used to write the clear register with one command and issue a clear to the board.

Parameters:

hBoard:	device handle
ClearValue:	1 - 65535

ClockDivisor6430

```
void ClockDivisor6430(RTDHANDLE hBoard, uchar8 Timer, uint16 Divisor);
```

Description:

This routine is used to set the divisor of a designated counter on the 8254 programmable interval timer (PIT). This procedure assumes that the counter has already been set to receive the least significant uchar8 (LSB) of the divisor followed by the most significant uchar8 (MSB).

Parameters:

hBoard:	device handle
Timer:	0,1,2
Divisor:	0 - 65535

ClockMode6430

```
void ClockMode6430(RTDHANDLE hBoard, uchar8 Timer, uchar8 Mode);
```

Description:

This routine is used to set the mode of a designated counter in the 8254 programmable interval timer (PIT).

Parameters:

hBoard:	device handle
Timer:	0,1,2
Mode:	0,1,2,3,4,5

CloseBoard6430

```
BOOL CloseBoard6430 (LONG DEVICE_NO, LPSTR szBuf);
```

Description:

This routine is used to close board driver.

Parameters:

DeviceNumber:	WinRT device number to load
szBuf:	message buffer

Return value:

TRUE on success, FALSE on error

ConfigDINClock6430

```
void ConfigDINClock6430(RTDHANDLE hBoard, uint16 DIN_Clock);
```

Description:

This routine configures the Digital Input FIFO clock source.

Parameters:

hBoard:	device handle
DIN_Clock:	0 = user T/C out 0
	1 = user T/C out 1
	2 = write A/D FIFO
	3 = external pacer clock
	4 = external trigger
	5 = reserved
	6 = reserved
	7 = reserved

DeInstallDMA6430

```
BOOL DeInstallDMA6430(RTDHANDLE hBoard, int dma_ch_index);
```

Description:

This routine is used to remove DMA handler.

Parameters:

hBoard: device handle
dma_ch_index: DMA channel index (0/1)

Returns:

0 if success
error code if not success

DINClockEnable6430

```
void DINClockEnable6430(RTDHANDLE hBoard, uint16 DIN_Clock);
```

Description:

This routine enables the Digital Input FIFO clock.

Parameters:

hBoard: device handle
DIN_Clock: 0 = disabled
 1 = enabled

DoneTimer6430

```
void DoneTimer6430(RTDHANDLE hBoard);
```

Description:

Initialize the timers for high speed to ensure the immediate load.

Parameters:

hBoard: device handle

EnableIrq5812_6430

```
void EnableIrq5812_6430(RTDHANDLE hBoard, uchar8 SelectedChip, uchar8 Enable);
```

Description:

This routine enables the selected DIO chips interrupt.

Parameters:

hBoard:	device handle
SelectedChip:	0, 1, 2
Enable:	0 = Disabled 1 = Enabled

EnableTables6430

```
void EnableTables6430(RTDHANDLE hBoard, uint16 Enable_AD_Table, uint16  
    Enable_Digital_Table);
```

Description:

This Routine Enables and Disables both the AD and Digital Tables.

Parameters:

hBoard:	device handle
Enable_AD_Table:	0 = disable 1 = enable
Enable_Digital_Table:	0 = disable 1 = enable

FlushDMA6430

```
void FlushDMA6430(RTDHANDLE hBoard);
```

Description:

This routine flushes the DMA buffer.

Parameters:

hBoard: device handle

GetAutoincDataByte6430

```
BOOL GetAutoincDataByte6430(RTDHANDLE hBoard, AutoincSetup *autoincsetup, uint16  
    DataNum);
```

Description:

This routine is used to get the data with autoincrement driver mode.
It uses the INP_B command to read data.

Parameters:

hBoard:	device handle
autoincsetup:	parameters for autoincrement command
DataNum:	number of data item to read

Return value:

TRUE on success, FALSE on error

GetAutoincDataWord6430

```
BOOL GetAutoincDataWord6430(RTDHANDLE hBoard, AutoincSetup *autoincsetup, uint16  
    DataNum);
```

Description:

This routine is used to get the data with autoincrement driver mode.
It uses the INP_W command to read data.

Parameters:

hBoard:	device handle
autoincsetup:	parameters for autoincrement command
DataNum:	number of data item to read

Return value:

TRUE on success, FALSE on error

GetErrorStatus6430

```
BOOL GetErrorStatus6430 ( RTDHANDLE hBoard, LONG *ErrorCode ,  
    LPSTR ErrorString);
```

Description:

This routine is used to get the error code and string in case of errors.
The function clears the last error code.

Parameters:

hBoard:	device handle
ErrorCode:	Error Code
ErrorString:	Return error string

GetIRQCounter6430

```
void GetIRQCounter6430(RTDHANDLE hBoard, IRQSetup *irqsetup);
```

Description:

This routine is used to get the counter incremented by IRQ.

Parameters:

hBoard:	device handle
irqsetup:	return parameters to caller

InitBoard6430

```
void InitBoard6430(RTDHANDLE hBoard);
```

Description:

This Routine Should always be called first.
This clears the board and variables the driver uses.

Parameters:

hBoard:	device handle
---------	---------------

InstallCallbackIRQHandler6430

```
BOOL InstallCallbackIRQHandler6430 (RTDHANDLE hBoard, isr_t handler);
```

Description:

This routine is used to install IRQ handler function.

Parameters:

hBoard:	device handle
isrT handler:	user callback function

Return value:

TRUE on success, FALSE on error

InstallCounterIRQHandler6430

```
BOOL InstallCounterIRQHandler6430(RTDHANDLE hBoard, IRQSetup *irqsetup);
```

Description:

This routine is used to install IRQ handler function.

Parameters:

hBoard:	device handle
irqsetup:	return parameters to caller

Return value:

TRUE on success, FALSE on error

InstallDMA6430

```
BOOL InstallDMA6430(RTDHANDLE hBoard, DMASetup *dmasetup, BOOL fill,  
                    UCHAR fill_byte, int dma_ch_index);
```

Description:

This routine is used to install DMA handler.

Parameters:

hBoard:	device handle
dmasetup:	return parameters to caller
fill:	TRUE if buffer fill is necessary
fill_byte:	DMA buffer filler
dma_ch_index:	DMA channel index (0/1)

Return value:

TRUE on success, FALSE on error

IsAboutTrigger6430

```
uint16 IsAboutTrigger6430(RTDHANDLE hBoard);
```

Description:

This routine checks to see if the about trigger has occurred.

Parameters:

hBoard:	device handle
---------	---------------

Returns:

1 if trigger has occurred
0 if trigger has not occurred

IsADConverting6430

```
uint16 IsADConverting6430(RTDHANDLE hBoard);
```

Description:

This routine checks to see if the AD converting.

Parameters:

hBoard:	device handle
---------	---------------

Returns:

1 if AD is converting
0 if AD is not converting

IsADDMADone6430

```
uint16 IsADDMADone6430(RTDHANDLE hBoard);
```


Description:

This routine checks to see if the A/D DMA transfer is done.

Parameters:

hBoard: device handle

Returns:

1 if DMA is done
0 if DMA is not done

IsADFIFOEmpty6430

uint16 IsADFIFOEmpty6430(RTDHANDLE hBoard);

Description:

This routine checks to see if the A/D FIFO is empty.

Parameters:

hBoard: device handle

Returns:

1 if FIFO is empty
0 if FIFO is not empty

IsADFIFOFull6430

uint16 IsADFIFOFull6430(RTDHANDLE hBoard);

Description:

This routine checks to see if the A/D FIFO is full.

Parameters:

hBoard: device handle

Returns:

1 if FIFO is full
0 if FIFO is not full

IsADHalted6430

uint16 IsADHalted6430(RTDHANDLE hBoard);

Description:

This routine checks to see if the AD is halted.

Parameters:

hBoard: device handle

Returns:

1 if AD is halted
0 if AD is not halted

IsBurstClockOn6430

uint16 IsBurstClockOn6430(RTDHANDLE hBoard);

Description:

This routine checks to see if the burst clock is enabled.

Parameters:

hBoard: device handle

Returns:

1 if Burst Clock is on
0 if Burst Clock is off

IsChipIRQ5812_6430

uchar8 IsChipIrq5812_6430(RTDHANDLE hBoard, uchar8 SelectedChip);

Description:

This routine checks to see if the selected DIO chip has generated an interrupt.

Parameters:

hBoard: device handle
SelectedChip: 0, 1, 2

Returns:

1 if IRQ has been generated
0 if no IRQ

IsDigitalIRQ6430

uint16 IsDigitalIRQ6430(RTDHANDLE hBoard);

Description:

This routine checks to see if the digital I/O chip has generated an interrupt.

Parameters:

hBoard: device handle

Returns:

1 if IRQ has been generated
0 if no IRQ

IsDINFIFOEmpty6430

uint16 IsDINFIFOEmpty6430(RTDHANDLE hBoard);

Description:

This routine checks to see if the Digital Input FIFO is empty.

Parameters:

hBoard: device handle

Returns:

1 if FIFO is empty
0 if FIFO is not empty

IsDINFIFOFull6430

uint16 IsDINFIFOFull6430(RTDHANDLE hBoard);

Description:

This routine checks to see if the Digital Input FIFO is full.

Parameters:

hBoard: device handle

Returns:

1 if FIFO is full
0 if FIFO is not full

IsDINFIFOHalf6430

uint16 IsDINFIFOHalf6430(RTDHANDLE hBoard);

Description:

This routine checks to see if the Digital Input FIFO is half full.

Parameters:

hBoard: device handle

Returns:

1 if FIFO is half full
0 if FIFO is not half full

IsFirstADDMADone6430

uint16 IsFirstADDMADone6430(RTDHANDLE hBoard);

Description:

This routine checks to see if the A/D DMA transfer is done on the first channel.

Parameters:

hBoard: device handle

Returns:

1 if DMA is done
0 if DMA is not done

IsIRQ16430

uint16 IsIRQ16430(RTDHANDLE hBoard);

Description:

This routine checks the IRQ 1 status bit.

Parameters:

hBoard: device handle

Returns:

1 if IRQ has been generated
0 if no IRQ

IsIRQ26430

uint16 IsIRQ26430(RTDHANDLE hBoard);

Description:

This routine checks the IRQ 2 status bit.

Parameters:

hBoard: device handle

Returns:

1 if IRQ has been generated

0 if no IRQ

IsPacerClockOn6430

uint16 IsPacerClockOn6430(RTDHANDLE hBoard);

Description:

This routine checks to see if the pacer clock is running.

Parameters:

hBoard: device handle

Returns:

1 if Pacer Clock is on
0 if Pacer Clock is off

LoadADSampleCounter6430

```
LoadADSampleCounter6430(RTDHANDLE hBoard, uint16 NumOfSamples);
```

Description:

This routine loads the A/D sample counter.

Parameters:

hBoard: device handle
NumOfSamples: 0 - 65535

LoadADTable6430

```
void LoadADTable6430(RTDHANDLE hBoard, uint16 Num_of_Entry,  
ADTableRow *ADTable);
```

Description:

This routine loads the AD Table with the given number of entries.

Parameters:

hBoard: device handle
Num_of_Entry: 1-1024

The struct ADTableRow is defined in REG6430.h

```
typedef struct  
{  
    uint16 Channel: 0 - 15  
  
    uint16 Gain: 0 = x1  
               1 = x2  
               2 = x4  
               3 = x8  
               4 = reserved  
               5 = reserved  
               6 = reserved  
               7 = reserved  
  
    uint16 Se_Diff: 0 = single ended  
                  1 = differential  
  
    uint16 Pause: 0 = disabled  
                 1 = enabled  
  
    uint16 Skip: 0 = disabled  
                1 = enabled  
} ADTableRow;
```

LoadCompare5812_6430

void LoadCompare5812_6430(RTDHANDLE hBoard, uchar8 SelectedChip, uchar8 Compare);

Description:

This routine loads the selected DIO chips compare register.

Parameters:

hBoard:	device handle
SelectedChip:	0, 1, 2
Compare:	0 - 255

LoadControlRegister6430

void LoadControlRegister6430(RTDHANDLE hBoard, uint16 Value);

Description:

This routine loads the control register with one write operation.

Parameters:

hBoard:	device handle
Value:	0 - 65535

LoadDAC6430, LoadDAC26430

void LoadDAC6430(RTDHANDLE hBoard, int16 Data);
void LoadDAC26430(RTDHANDLE hBoard, int16 Data);

Description:

This routine loads the DAC value.

If the board is assembled with two D/A converters, the second DAC is accessible with the LoadDAC26430 function.

Parameters:

hBoard:	device handle
Data:	0 - 65535

LoadDigitalTable6430

void LoadDigitalTable6430(RTDHANDLE hBoard, uint16 Num_of_Channels, uchar8 *Channel);

Description:

This routine loads the Digital Table with the given number of entries.

Parameters:

hBoard:	device handle
---------	---------------

Channel: 0 - 255
Num_of_Channels: 1 - 1024

LoadDINConfigRegister6430

void LoadDINConfigRegister6430(RTDHANDLE hBoard, uint16 Value);

Description:

This routine loads the Digital Input configuration register with one write operation.

Parameters:

hBoard: device handle
Value: 0 - 65535

LoadIRQRegister6430

void LoadIRQRegister6430(RTDHANDLE hBoard, uint16 Value);

Description:

This routine loads the interrupt register with one write operation.

Parameters:

hBoard: device handle
Value: 0 - 65535

LoadMask5812_6430

void LoadMask5812_6430(RTDHANDLE hBoard, uchar8 SelectedChip, uchar8 Mask);

Description:

This routine loads the selected DIO chips mask register.

Parameters:

hBoard: device handle
SelectedChip: 0, 1, 2
Mask: 0 - 255

LoadTriggerRegister6430

void LoadTriggerRegister6430(RTDHANDLE hBoard, uint16 Value);

Description:

This routine loads the trigger register with one write operation.

Parameters:

hBoard: device handle

Value: 0 - 65535

OpenBoard6430

```
BOOL OpenBoard6430(int num, int device_id, LPSTR szBuf,  
    BoardConfig *boardconfig );
```

Description:

This routine is used to open board driver.

Parameters:

num: the number of the board
device_id: 6430h (hexadecimal)
szBuf: return string
BoardConfig: Return board configuration

Return value:

TRUE on success, FALSE on error

ReadADData6430

```
int16 ReadADData6430(RTDHANDLE hBoard);
```

Description:

This Routine Reads the Data from the FIFO.

Parameters:

hBoard: device handle

Returns:

16 bit AD Data.

ReadChannelGainDataStore6430

```
uint16 ReadChannelGainDataStore6430(RTDHANDLE hBoard);
```

Description:

This Routine Reads the Channel/Gain Data from the FIFO when the Channel Gain Data Store feature of the board is enabled.

Parameters:

hBoard: device handle

Returns:

16 bit value: Bottom 8 bits = A/D table value
Upper 8 bits = digital table value

ReadCompareRegister5812_6430

```
uchar8 ReadCompareRegister5812_6430(RTDHANDLE hBoard, uchar8 SelectedChip);
```

Description:

This routine reads the selected DIO chips compare register.

Parameters:

hBoard: device handle
SelectedChip: 0, 1, 2

ReadDINFIFO6430

```
uint16 ReadDINFIFO6430(RTDHANDLE hBoard);
```

Description:

This Routine Reads the Data from the Digital Input FIFO.

Parameters:

hBoard: device handle

Returns:

8 bit value.

ReadDIO5812_6430

uchar8 ReadDIO5812_6430(RTDHANDLE hBoard, uchar8 SelectedChip, uchar8 Port);

Description:

This routine reads the selected DIO chips port.

Parameters:

hBoard: device handle
SelectedChip: 0, 1, 2
Port: 0, 1

ReadStatus6430

uint16 ReadStatus6430(RTDHANDLE hBoard);

Description:

This routine returns the status from the board.

Parameters:

hBoard device handle

Returns:

16 bit unsigned integer

ReadTimerCounter6430

uint16 ReadTimerCounter6430(RTDHANDLE hBoard, uchar8 Timer, uchar8 Clock);

Description:

This routine is used to read the contents of the selected timer/counter.

Parameters:

hBoard: device handle

Timer: 0,1
Clock: 0,1,2

Returns:

uint16

RemoveIRQHandler6430

void RemoveIRQHandler6430(RTDHANDLE hBoard);

Description:

This routine is used to uninstall IRQ handler function.

Parameters:

hBoard: device handle

ResetChannelGainTable6430

void ResetChannelGainTable6430(RTDHANDLE hBoard);

Description:

This routine is used to reset both the AD Table and the Digital Table pointers to the first location in the table.

Parameters:

hBoard: device handle

SelectClock5812_6430

```
void SelectClock5812_6430(RTDHANDLE hBoard, uchar8 SelectedChip, uchar8 Clock);
```

Description:

This routine sets the selected DIO chips clock source.

Parameters:

hBoard:	device handle
SelectedChip:	0, 1, 2
Clock:	0 = 8 MHz 1 = Programmable clock

SelectIrqMode5812_6430

```
void SelectIrqMode5812_6430(RTDHANDLE hBoard, uchar8 SelectedChip, uchar8 IrqMode);
```

Description:

This routine sets the selected DIO chips Irq mode.

Parameters:

hBoard:	device handle
SelectedChip:	0, 1, 2
IrqMode:	0 = Event mode 1 = Match mode

SelectRegister5812_6430

```
void SelectRegister5812_6430(RTDHANDLE hBoard, uchar8 SelectedChip, uchar8 Select);
```

Description:

This routine picks the different registers on the selected DIO chip.

Parameters:

hBoard:	device handle
SelectedChip:	0, 1, 2
Select:	0 = Clear mode 1 = Port 0 direction 2 = Port 0 mask 3 = Port 0 compare

SelectTimerCounter6430

```
void SelectTimerCounter6430(RTDHANDLE hBoard, uint16 Select);
```

Description:

This routine selects one of the four 8254 timer chips.

Parameters:

hBoard:	device handle
Select:	0 = Clock TC (Pacer & Burst clocks)
	1 = User TC (A/D sample counter & User timer/counters)
	2 = reserved
	3 = reserved

SetADDMA6430

```
void SetADDMA6430(RTDHANDLE hBoard, uint16 Channel1, uint16 Channel2);
```

Description:

This routine sets the A/D DMA channels.

Parameters:

hBoard:	device handle
Channel1:	0 = disabled
	5 = DRQ 5
	5 = DRQ 6
	7 = DRQ 7
Channel2:	0 = disabled
	5 = DRQ 5
	6 = DRQ 6
	7 = DRQ 7

SetADPauseEnable6430

```
void SetPauseEnable6430(RTDHANDLE hBoard, uint16 Enable);
```

Description:

This routine enables and disables the A/D pause bit.

Parameters:

hBoard:	device handle
Enable:	0 = Enable
	1 = Disable

SetADSampleCounterStop6430

```
void SetSampleCounterStop6430(RTDHANDLE hBoard, uint16 Enable);
```

Description:

This routine enables and disables the A/D sample counter stop bit.

Parameters:

hBoard: device handle
Enable: 0 = Enable
1 = Disable

SetBurstClock6430

float32 SetBurstClock6430(RTDHANDLE hBoard, float32 BurstRate);

Description:

This routine sets the burst clock rate.

Parameters:

hBoard: device handle
Burst Rate: 100 KHz or less

Returns:

The actual clock frequency that is programmed.

SetBurstTrigger6430

void SetBurstTrigger6430(RTDHANDLE hBoard, uint16 Burst_Trigger);

Description:

This routine selects the burst trigger.

Parameters:

hBoard: device handle
Burst_Trigger: 0 = Software trigger
1 = pacer clock
2 = external trigger
3 = digital interrupt

SetChannelGain6430

void SetChannelGain6430(RTDHANDLE hBoard, uint16 Channel, uint16 Gain, uint16 Se_Diff);

Description:

This routine loads the channel/gain latch.

Parameters:

hBoard: device handle
Channel: 0 - 15
Gain: 0 = x1
1 = x2
2 = x4

	3 = x8
	4 = reserved
	5 = reserved
	6 = reserved
	7 = reserved
Se_Diff:	0 = single ended
	1 = differential

SetConversionSelect6430

```
void SetConversionSelect6430(RTDHANDLE hBoard, uint16 Select);
```

Description:

This routine selects the conversion mode.

Parameters:

hBoard:	device handle
Select:	0 = software trigger
	1 = pacer clock
	2 = burst clock
	3 = digital interrupt

SetIRQ1_6430

```
void SetIRQ1_6430(RTDHANDLE hBoard, uint16 Source, uint16 Channel);
```

Description:

This routine sets the source and channel for interrupt 1.

Parameters:

hBoard:	device handle
Source:	0 = A/D sample counter
	1 = A/D start convert
	2 = A/D End-of-Convert
	3 = A/D Write FIFO
	4 = A/D FIFO half full
	5 = A/D DMA done
	6 = Reset channel/gain table
	7 = Pause channel/gain table
	8 = External Pacer Clock
	9 = External trigger
	10 = Digital chip interrupt
	11 = User TC out 0
	12 = User TC out 0 inverted
	13 = User TC out 1
	14 = Digital Input FIFO half full
	15 = DIN Write FIFO
	16 .. 31 = reserved
Channel:	0 = disabled

3 = IRQ 3
5 = IRQ 5
9 = IRQ 9
10 = IRQ 10
11 = IRQ 11
12 = IRQ 12
15 = IRQ 15

SetIRQ2_6430

void SetIRQ2_6430(RTDHANDLE hBoard, uint16 Source, uint16 Channel);

Description:

This routine sets the source and channel for interrupt 2.

Parameters:

hBoard:	device handle
Source:	0 = A/D sample counter 1 = A/D start convert 2 = A/D End-of-Convert 3 = A/D Write FIFO 4 = A/D FIFO half full 5 = A/D DMA done 6 = Reset channel/gain table 7 = Pause channel/gain table 8 = External Pacer Clock 9 = External trigger 10 = Digital chip interrupt 11 = User TC out 0 12 = User TC out 0 inverted 13 = User TC out 1 14 = Digital Input FIFO half full 15 = DIN Write FIFO 16 .. 31 = reserved
Channel:	0 = disabled 3 = IRQ 3 5 = IRQ 5 9 = IRQ 9 10 = IRQ 10 11 = IRQ 11 12 = IRQ 12 15 = IRQ 15

SetPacerClock6430

float32 SetPacerClock6430(RTDHANDLE hBoard, float32 ClockRate);

Description:

This routine sets the pacer clock rate. It will automatically decide whether to use a 16 or 32 bit clock depending on the rate.

Parameters:

hBoard:	device handle
ClockRate:	100 KHz or less

Returns:

The actual clock frequency that is programmed.

SetPacerClockSource6430

```
void SetPacerClockSource6430(RTDHANDLE hBoard, uint16 Source);
```

Description:

This routine sets the pacer clock source.

Parameters:

hBoard:	device handle
Source:	0 = Internal 1 = External

SetPort0Direction5812_6430

```
void SetPort0Direction5812_6430(RTDHANDLE hBoard, uchar8 SelectedChip,  
                                uchar8 Direction);
```

Description:

This routine sets the selected DIO chips port 0 direction.

Parameters:

hBoard:	device handle
SelectedChip:	0, 1, 2
Direction:	0 - 255 0 = In 1 = Out

SetPort1Direction5812_6430

```
void SetPort1Direction5812_6430(RTDHANDLE hBoard, uchar8 SelectedChip,  
                                uchar8 Direction);
```

Description:

This routine sets the selected DIO chips port 1 direction.

Parameters:

hBoard:	device handle
SelectedChip:	0, 1, 2

Direction: 0 = In
 1 = Out

SetStartTrigger6430

void SetStartTrigger6430(RTDHANDLE hBoard, uint16 Start_Trigger);

Description:

This routine selects the start trigger.

Parameters:

hBoard: device handle
Start_Trigger: 0 = software trigger
 1 = external trigger
 2 = digital interrupt
 3 = User TC Counter 1 out
 4 = reserved
 5 = reserved
 6 = reserved
 7 = gate mode

SetStopTrigger6430

void SetStopTrigger6430(RTDHANDLE hBoard, uint16 Stop_Trigger);

Description:

This routine selects the stop trigger.

Parameters:

hBoard: device handle
Stop_Trigger: 0 = software trigger
 1 = external trigger
 2 = digital interrupt
 3 = sample counter
 4 = about software trigger
 5 = about external trigger
 6 = about digital interrupt
 7 = about user TC counter 1 out

SetTriggerPolarity6430

void SetTriggerPolarity6430(RTDHANDLE hBoard, uint16 Polarity);

Description:

This routine sets the external trigger polarity.

Parameters:

hBoard: device handle

Polarity: 0 = positive edge
 1 = negative edge

SetTriggerRepeat6430

```
void SetTriggerRepeat6430(RTDHANDLE hBoard, uint16 Repeat);
```

Description:

This routine sets the trigger repeat bit.

Parameters:

hBoard: device handle
Repeat: 0 = Single Cycle
 1 = Repeat Cycle

SetUserClock6430

```
float32 SetUserClock6430(RTDHANDLE hBoard, uchar8 Timer, float32 InputRate,  
                          float32 OutputRate);
```

Description:

This routine sets the user timer counters.

Parameters:

hBoard: device handle
Timer: 0, 1, 2
InputRate: Input clock to selected timer.
OutputRate: Desired output rate from selected timer.

Returns:

The actual clock frequency that is programmed.

StartConversion6430

```
void StartConversion6430(RTDHANDLE hBoard);
```

Description:

This routine is used to create software triggers or enable hardware triggers depending on the conversion mode.

Parameters:

hBoard: device handle

StartDMA6430

```
void StartDMA6430(RTDHANDLE hBoard, ULONG UserLength, int dma_ch_index);
```

Description:

This routine starts DMA.

Parameters:

hBoard:	device handle
UserLengt:	user definable dma length
dma_ch_index:	DMA channel index (0/1)

WriteDIO5812_6430

```
void WriteDIO5812_6430(RTDHANDLE hBoard, uchar8 SelectedChip, uchar8 Port,  
                      uchar8 Data);
```

Description:

This routine writes the selected DIO chips port.

Parameters:

hBoard:	device handle
SelectedChip:	0, 1, 2
Port:	0, 1
Data:	0 - 255

Example Programs Reference

Win32 console applications

Name	Feature	Remarks
dma	Single DMA channel acquisition Sampling on pacer clock Start trigger: software Stop trigger: software	The data is displayed numerically on the screen.
speedtst	Sampling on pacer clock Start trigger: software Stop trigger: software Using IRQ handler function	It demonstrates three methods of data acquisition with interrupt: <ul style="list-style-type: none">• callback function• poll the IRQ counter• get data with autoincrement mode

Win32 Windows applications

Name	Feature	Remarks
wdac	Digital/analog conversation.	The user can change the output voltage with the on-screen slider.
wdigital	It programs the digital port 0 to input, port 1 to output.	The user can set the digital output port; the program reads the input port.
wdma	Single DMA channel acquisition. Sampling on pacer clock Start trigger: software Stop trigger: software	The data displayed graphically on the screen.
wdualdma	Dual DMA channel acquisition. Sampling on pacer clock Start trigger: software Stop trigger: software	It demonstrates the high speed gap-free data acquisition. The data stored in file.
whidin	High-speed digital input example. The user timer-counter is programmed to sample the digital input. At digital FIFO half full generated an interrupt, and the data is stored and displayed.	The data displayed graphically and stored in file.
wintrpts	The user timer-counter is programmed to generate interrupts. The analog input sampled when the IT occurs.	The data displayed graphically.
wrandom	Random channel acquisition with CGT. The pacer clock programmed to start conversion with burst clock.	The samples are displayed numerically.
wrepinsw	Sampling on pacer clock. Start trigger: software Stop trigger: software Interrupt on sample counter	On sample counter IT the program reads and displays the samples graphically.
wmpcnt	Sampling on pacer clock. Start trigger: software Stop trigger: sample counter. Interrupt on sample counter	On sample counter IT the program reads and displays the samples graphically. The user can repeat the measure by pressing a key.
wsofttrig	Single A/D sampling. Start trigger: software Stop trigger: software	The user can sample an analog input by pressing a button. The sample displayed on the screen in Volts.
w2board	Example on how to use two boards.	Demonstration of the driver's multi-board feature.
wtimers	Demonstration of user timer-counters.	The counters are programmed to count the elapsed time in seconds.

Limited Warranty

RTD Embedded Technologies, Inc. warrants the hardware and software products it manufactures and produces to be free from defects in materials and workmanship for one year following the date of shipment from RTD Embedded Technologies, INC. This warranty is limited to the original purchaser of product and is not transferable.

During the one year warranty period, RTD Embedded Technologies will repair or replace, at its option, any defective products or parts at no additional charge, provided that the product is returned, shipping prepaid, to RTD Embedded Technologies. All replaced parts and products become the property of RTD Embedded Technologies. Before returning any product for repair, customers are required to contact the factory for an RMA number.

THIS LIMITED WARRANTY DOES NOT EXTEND TO ANY PRODUCTS WHICH HAVE BEEN DAMAGED AS A RESULT OF ACCIDENT, MISUSE, ABUSE (such as: use of incorrect input voltages, improper or insufficient ventilation, failure to follow the operating instructions that are provided by RTD Embedded Technologies, "acts of God" or other contingencies beyond the control of RTD Embedded Technologies), OR AS A RESULT OF SERVICE OR MODIFICATION BY ANYONE OTHER THAN RTD Embedded Technologies. EXCEPT AS EXPRESSLY SET FORTH ABOVE, NO OTHER WARRANTIES ARE EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, ANY IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, AND RTD Embedded Technologies EXPRESSLY DISCLAIMS ALL WARRANTIES NOT STATED HEREIN. ALL IMPLIED WARRANTIES, INCLUDING IMPLIED WARRANTIES FOR MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, ARE LIMITED TO THE DURATION OF THIS WARRANTY. IN THE EVENT THE PRODUCT IS NOT FREE FROM DEFECTS AS WARRANTED ABOVE, THE PURCHASER'S SOLE REMEDY SHALL BE REPAIR OR REPLACEMENT AS PROVIDED ABOVE. UNDER NO CIRCUMSTANCES WILL RTD Embedded Technologies BE LIABLE TO THE PURCHASER OR ANY USER FOR ANY DAMAGES, INCLUDING ANY INCIDENTAL OR CONSEQUENTIAL DAMAGES, EXPENSES, LOST PROFITS, LOST SAVINGS, OR OTHER DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE PRODUCT.

SOME STATES DO NOT ALLOW THE EXCLUSION OR LIMITATION OF INCIDENTAL OR CONSEQUENTIAL DAMAGES FOR CONSUMER PRODUCTS, AND SOME STATES DO NOT ALLOW LIMITATIONS ON HOW LONG AN IMPLIED WARRANTY LASTS, SO THE ABOVE LIMITATIONS OR EXCLUSIONS MAY NOT APPLY TO YOU.

THIS WARRANTY GIVES YOU SPECIFIC LEGAL RIGHTS, AND YOU MAY ALSO HAVE OTHER RIGHTS WHICH VARY FROM STATE TO STATE.

RTD Embedded Technologies, Inc.
103 Innovation Blvd.
State College PA 16803-0906
USA
Our website: www.rtd.com